

Logistic Regression: nagdmc_logit_reg

Purpose

nagdmc_logit_reg computes a logistic regression model with p parameters and is a simplified interface to **nagdmc_binomial_reg** using a logit link function.

Declaration

```
#include <nagdmc.h>

void nagdmc_logit_reg(long rec1, long nvar, long nrec, long dblk, double data[],
                     long nxvar, long xvar[], long yvar, double ycut, long bdvar,
                     double *dev, long *df, double b[], double se[], double cov[],
                     double model[], int *info);
```

Parameters

- 1: **rec1** – long *Input*
On entry: the index in the data of the first data record used in the analysis.
Constraint: **rec1** ≥ 0 .
- 2: **nvar** – long *Input*
On entry: the number of variables in the data.
Constraint: **nvar** > 1 .
- 3: **nrec** – long *Input*
On entry: the number of consecutive records, beginning at **rec1**, used in the analysis.
Constraint: **nrec** > 1 .
- 4: **dblk** – long *Input*
On entry: the total number of records in the data block.
Constraint: **dblk** $\geq \text{rec1} + \text{nrec}$.
- 5: **data**[**dblk** * **nvar**] – double *Input*
On entry: the data values for the j th variable (for $j = 0, 1, \dots, \text{nvar} - 1$) are stored in **data**[$i * \text{nvar} + j$], for $i = 0, 1, \dots, \text{dblk} - 1$.
- 6: **nxvar** – long *Input*
On entry: the number of independent variables. If **nxvar** = 0 then all variables in the data, excluding **yvar** and (if ≥ 0) **bdvar**, are treated as independent variables.
Constraint: $0 \leq \text{nxvar} < \text{nvar}$.
- 7: **xvar**[**nxvar**] – long *Input*
On entry: the indices indicating the position in **data** in which values of the independent variables are stored. If **nxvar** = 0 then **xvar** must be 0, and the indices of independent variables are given by $j = 0, 1, \dots, \text{nvar} - 1$; $j \neq \text{yvar}$ and $j \neq \text{bdvar}$.
Constraints: if **nxvar** > 0 , $0 \leq \text{xvar}[i] < \text{nvar}$, for $i = 0, 1, \dots, \text{nxvar} - 1$; otherwise **xvar** must be 0.
- 8: **yvar** – long *Input*
On entry: the index in **data** in which values of the dependent variable are stored.
Constraints: $0 \leq \text{yvar} < \text{nvar}$; if **nxvar** > 0 , **yvar** $\neq \text{xvar}[i]$, for $i = 0, 1, \dots, \text{nxvar} - 1$.
- 9: **ycut** – long *Input*
On entry: if **ycut** $\neq 0$, the y -variable is transformed so that values $< \text{ycut}$ are set to zero and values $\geq \text{ycut}$ are set to one.

- 10: **bdvar** – long *Input*
On entry: an index indicating the position in **data** in which the binomial denominator is stored. If **bdvar** = –1 a default value of one is used for all observations.
Constraint: $-1 \leq \mathbf{bdvar} < \mathbf{nvar}$.
- 11: **dev** – double *Output*
On exit: the deviance from the fitted model.
- 12: **df** – long * *Output*
On exit: the degrees of freedom for the deviance.
- 13: **b[p]** – double *Output*
On exit: the parameter estimates. **b**[0] is the mean parameter. **b**[*i*] is the coefficient of the *i*th variable included in the model, for $i = 1, 2, \dots, p - 1$. If **nxvar** > 0 then the order the independent variables are added to the model is defined by **xvar**, otherwise the order is defined by indices in the data.
- 14: **se[p]** – double *Output*
On exit: the standard errors of the parameters in **b**.
- 15: **cov**[$p * (p + 1) / 2$] – double *Output*
On exit: the first $p * (p + 1) / 2$ elements of **cov** contain the upper triangular part of the variance-covariance matrix of the *p* parameters in **b**. They are stored packed by column, i.e., the covariance between the parameter estimate given in **b**[*i*] and the parameter estimate given in **b**[*j*], $j \geq i$, is stored in **cov**[$j(j + 1) / 2 + i$], for $i = 0, 1, \dots, p - 1$ and $j = i, i + 1, \dots, p - 1$.
- 16: **model**[($3 * p * (p + 1) / 2 + \mathbf{nvar} + 14$)] – double *Output*
On exit: if not 0, information on the fitted model for use in the functions described in ‘[See Also](#)’.
- 17: **info** – int * *Output*
On exit: **info** gives information on the success of the function call:
- 4: a model value has reached a boundary.
 - 0: the function successfully completed its task.
 - i*; $i = 1, 2, \dots, 4, 7, 8, 10$: the specification of the *i*th formal parameter was incorrect.
 - 42: invalid value for response variable.
 - 43: invalid value for binomial denominator.
 - 45: model has not converged.
 - 57: there are no degrees of freedom for the error estimates.
 - 58: the fit is exact, no error estimates.
 - 59: more variables than observations.
 - 98: there is an underlying computational problem (this is an unlikely error exit).
 - 99: the function failed to allocate enough memory.

Notation

nrec	the number of observations, <i>n</i> .
nxvar	the number of independent variables, $p - 1$.
xvar	the independent variables, <i>X</i> , excluding the mean.
yvar	the dependent variable, <i>y</i> .
bdvar	if bdvar ≥ 0, bdvar is the index in the data that defines the binomial denominator, <i>t</i> .
b	the parameter estimates, $\hat{\beta}$.

Description

See the description for [nagdmc_binomial_reg](#).

References and Further Reading

Cook R D and Weisberg S (1982) *Residuals and Influence in Regression* Chapman and Hall.

Cox D R (1983) *Analysis of Binary Data* Chapman and Hall.

McCullagh P and Nelder J A (1983) *Generalized Linear Models* Chapman and Hall.

See Also

nagdmc_binomial_reg	generalized linear model with binomial errors.
nagdmc_extr_reg	computes fitted values, residuals and leverages for a regression.
nagdmc_predict_reg	computes predictions given a fitted regression model.
nagdmc_probit_reg	simplified version of nagdmc_binomial_reg using a probit link and a restricted set of parameters.
logit_reg_ex.c	the example calling program.
